

**Adam** - BB & SR














## Overview Adam – BB & SR V4.00

- ✓ Principle: Price bounces back from a inverse S/R if outside BB
  - ✓ Buy: Price is over BB and bounces back from an old support
  - ✓ Sell: Price is under BB and bounces back from an old resistance
- ✓ TF: H1



## Settings: Overview

 _	===== All Star settings =====
 BB: use	true
 BB: period	20
 BB: deviation	2.0
 All Star: No of Candles left/right for peak	5
 All Star: Max. distance of the peaks	15
 All Star: No of points to start the trade from S/R	70
 SL: Distance from min last 5 Candles in points	10
 All Star: Type of TP	tp at upper(lower) BB
 RR ratio	3.0
 Trigger X bars before: How many Bars to look back for signal?	2

## Settings: BB

	BB: use	true
	BB: period	20
	BB: deviation	2.0

The settings of the BB's

## Settings: No of candles for determine the peaks

123 All Star: No of Candles left/right for peak	5
---	---

Peaks for S/R are the high/lows of the X candles left/right



5 5

We determine the S/R as levels of peaks which are the highest/lowest of X candles left/right; here we look 5 candles right/left

## Settings: Maximal distance

123 All Star: Max. distance high-low	15
--------------------------------------	----

Max. difference between new high and old low for signal(for sell) and vice versa!



For Sell: Maximal difference between the old Low(now Resistance) and the new High in points;  
In other words: It s the maximal difference of the high and low of the both peaks!

## Settings: Start Trade

123 All Star: No of points to start the trade from S/R	70
--	----

Max. difference between new high and old low for signal(for sell) and vice versa!




Trigger when the price is away from last high/low!

## Settings: SL of trades

123	SL: Distance from min last 5 Candles in points	100
-----	--	-----

Set the SL X



SL is set X Points from the min. of last 5 candles;  
sell vice versa: Xpoints from the max. of last 5 candles



## Settings: TP

123 All Star: Type of TP	tp at upper(lower) BB
1/2 RR ratio	no tp
	tp at upper(lower) BB
	tp as RR to SL

No TP; but you can set the standard fixed points or ADHR for TP!

Uses other side of BB Bands for TP

Uses the RR value(Standard: 3.0) for TP:  
TP has to be 3 times far away from entry than the SL!

## Settings: Start Trade

123

Trigger X bars before: How many Bars to look back for signal?

2

Number of bars to look back for a valid high/low

How long to look back for a valid signal!

