

## CONS EXPERT PARAMETERS SAFEBOT2.PRO3

(Beta July F)

closing deals line now called close1 and close 2, t\_close1 and t\_close2

comment in Expert	Value	Functional
working off Testing	Yes	Resolution mining type "setup" signal
setups extension	Yes	Resolution mining type "expansion" signal
Number packages BUY	-one	Specifies the number of packets (transactions) within the selected directions. 0 - the robot does not open a transaction direction BUY. -1 - the number of packets is not limited.
number packages SELL	-one	Specifies the number of packets (transactions) within the selected directions. 0 - the robot does not open a transaction direction SELL. -1 - the number of packets is not limited.
The percentage of risk (%)	1.0	The percentage of the risk of the current account in determining the amount lot
maximum Drawdown (%)	50.0	Planting a percentage of the current account in which happens trading stops (transaction closed trades are prohibited)
Take profit (paragraph)	twenty	Standard value arrived in paragraphs 4 char. for a single dealings
The number of signals	4	A parameter that is used to generate signals
start time <u>Expert advisor</u>	00:00	Specifies the time range of the expert work. new deal are opened in a predetermined range. New transaction open package can be opened at other times.
end time <u>Expert advisor</u>	00:00	
	11111	
		number of experts
The boundary of the beginning trawl (in claims)	one hundred	When the trailing transaction value in paragraph 4 char. to convert feet loss (SL) warrants
The border <u>pulling (in claims)</u> line with closing candles	40	Tightening border trailing. The value in the receptacle 4. points which is set when changing SL
	not	Refines control lines crossing control. at inclusion check is performed only at the close of the next candle
Fixed unit of trading	0.1	When determining (not equal to 0) to the transaction are always opened only specify the lot. When = 0 lot size is calculated from the shopping context
Maximum initial Offer	1.0	Maximum initial auction package deals. If the calculated lot size would be> the maximum, it will select a maximum initial
Calibration (for Exotic. tools)	not	For some instruments, there is no value price points. They are It can be calculated (but not exactly). Calibration - calculation commodity price point
Dynamic Profit (0-No, 1-profit)	0	Specifies whether to use (read) dynamic Profit for a single transaction. Use the ATR indicator

Base tool	EURUSD	Designation current base tool (EURUSD) for current broker (possible suffixes)
profit stepper period (%)	one hundred	Upon reaching a predetermined percentage of the profit from the transaction balance closed, trade is stopped at a specific time
pause between periods (h)	2	Pause time (in hours) between the preparation predetermined periods <u>% profit</u>
solve horizontal the starting line (Start_)	DON'T_USE, SIMPLE, NEED_CROSS	These horizontal lines define the terms and scope opening orders corresponding types. to permit the intersection of the corresponding line: for BUY - start_buy, to SELL - start_sell. Permitted mining area is the area below the signal level start_sell and higher for start_buy. Testing of the line (the resolution) is regulated parameter  "Allow the starting line (start_). 2 modes are available, "working off" line - the direct location in relation line (SIMPLE) and a mode where you must first of its intersection (NEED_CROSS).
solve trend the starting line (Trend_)	DON'T_USE, SIMPLE, NEED_CROSS	These trend lines define the terms and scope opening orders. For permit order opening of the appropriate type must be the intersection of the corresponding line: for BUY - trend_buy, to SELL - trend_sell. Permitted mining area is the area below the signal level trend_sell and higher for trend_buy. Testing of the line (the resolution) is regulated parameter  "Allow the starting line (start_). 2 modes are available, "working off" line - the direct location in relation line (SIMPLE) and a mode where you must first of its intersection (NEED_CROSS).
Lot of default next orders	0.2	Syntax forced the refill position nextsell_lot  The value can be any nextsell suffix, e.g. nextsell1, nextsell2, nextsell100. The main thing is to have a root name nextsell.  If the sign _ Set the lot, the robot opens the transaction is the lot that is specified. If the name is nextsell format (without a lot), the robot will take the item from the default for this field.  The same rule applies to nextbuy lines.
allow work from rectangular shopping areas	false	To control trading process on the terminal may be placed rectangular areas with a fixed name. Title Format: buy [sell] # N_Mgde N - divider standard lots, M - number of transactions (packets) in pyramougolnike.Vzavisimostiotimenioblasti adjusted lot size orders and the number of transactions within it.
work with channels	False	Canal - one of the basic operational structures. It has Triplex structure. Characterized by an angle of inclination, width and lifetime.  The channels are constructed automatically according to set parameters. The main parameter - the channel width (in points 4 char.)

		Calculated channels can be displayed on the trading terminal or mb invisible. This parameter is responsible for the display of the channel on the chart.
The height of the channel	320	Tries to draw a trend channel desired height (in Nos. 4 characters)
profit package closing (% of balance)	2	Allow the forced closure of the pack. It operates at reaching a predetermined profit of the current packet in otrderov% (Next parameter). When the preset% profit the whole package of orders opened and closed with one warrant ½ package volume and calculated the appropriate stop ½ profit closed package.
Show panel buttons	true	Shows the button bar to work with the lines (on the left bottom corner of the chart)
use functional <u>line tester</u>	true	It is recommended to disable this option to work in the tester non-imaging mode (for faster test time).
Colors control lines		Setting line color for keypad.